

# **Exclaimer Anti-spam**System Requirements

# **Installing on a Hub Transport Server**

#### Hardware

Component	Minimum Requirements	Recommended Requirements
CPU	x64 architecture-based computer. Intel Itanium family IA64 processors are not supported.	x64 architecture-based computer. Intel Itanium family IA64 processors are not supported.
Memory	1GB	4GB
Disk Space	350MB	500MB
Screen Resolution	1024 x 768	1152 x 864 or higher

#### **Software**

Component	Minimum Requirements
Operating System	<ul> <li>Windows Server 2003 R2 x64 (including all service pack levels).</li> <li>Windows Server 2008 x64 (including all service pack levels).</li> <li>Windows Server 2008 R2 x64 (including all service pack levels).</li> <li>Windows Server 2012.</li> <li>Windows Small Business Server 2008.</li> <li>Windows Small Business Server 2011.</li> </ul>
Active Directory Forest	Active Directory must be at Windows Server 2003 forest functionality level or higher.
Microsoft Exchange Server	<ul> <li>Microsoft Exchange Server 2007 SP1 Rollup 5 and above.</li> <li>Microsoft Exchange Server 2010 (including all service pack and rollup levels).</li> <li>Microsoft Exchange Server 2013.</li> </ul>
Microsoft Exchange Server Roles	Microsoft Exchange Hub Transport Role.
Microsoft .Net Framework	Microsoft .Net Framework 3.5 SP1 and above. (Exchange 2007 and 2010) Microsoft .Net Framework 4.5 (Exchange 2013)

# **Installing on an Edge Transport Server**

## Hardware

Component	Minimum Requirements	Recommended Requirements
CPU	x64 architecture-based computer. Intel Itanium family IA64 processors are not supported.	x64 architecture-based computer. Intel Itanium family IA64 processors are not supported.
Memory	1GB	4GB
Disk Space	350MB	500MB
Screen Resolution	1024 x 768	1152 x 864 or higher

## Software

Component	Requirement	
Operating System	<ul> <li>Windows Server 2003 R2 x64 (including all service pack levels).</li> <li>Windows Server 2008 x64 (including all service pack levels).</li> <li>Windows Server 2008 R2 x64 (including all service pack levels).</li> <li>Windows Server 2012.</li> </ul>	
Active Directory Forest	Active Directory must be at Windows Server 2003 forest functionality level or Active Directory Application Mode (ADAM) or Active Directory Lightweight Directory Services (ADLDS).	
Microsoft Exchange Server	<ul> <li>Microsoft Exchange Server 2007 SP1 Rollup 5 and above.</li> <li>Microsoft Exchange Server 2010 (including all service pack and rollup levels).</li> </ul>	
Microsoft Exchange Server Roles	Microsoft Exchange Edge Transport Role.	
Microsoft .Net Framework	Microsoft .Net Framework 3.5 SP1 and above.	